


How to Install a Sleeve Placket


1. **STAYSTITCH** vent opening lines, taking a stitch across the point (dot). Cut through center of vent opening to dot.




2. With wrong sides together, fold Sleeve Placket in half lengthwise and press.




3. Place folded Sleeve Placket to right side of vent opening. Open vent and position staystitching line $\frac{3}{8}$ " from raw edges of Placket. Sew evenly from outside edge of Placket and just to left of previous staystitching. Trim seam to $\frac{1}{8}$ ". Press seam towards Placket. Trim excess ends of Placket.



4. Turn folded edge of Sleeve Placket to *wrong* side of Sleeve, just covering previous stitching. Sew close to folded edge pivoting at dot and re-positioning opening and Placket in order to sew a straight line.



5. On inside of Sleeve, fold Placket at dot. Sew a 45° angle at top of Placket fold.



6. On side of vent closest to center of Sleeve, turn Placket to wrong side and baste at bottom.

