Plaza Vest


Pattern Adjustments:


Balancing Shoulder:


- •Subtract $\frac{1}{4}$ "- $\frac{1}{2}$ " (or desired amount) from Front Shoulder Seam on Front (1)
- •Add 1/4"-1/2" (or desired amount) to Back Shoulder Seam on Back (2)
- •Add 1/4"-1/2" (or desired amount) to Back Neck Band (3)
- *make sure to replace your pattern markings after each adjustment

Taking Fullness out of Garment:

•Remove 5" from garment width by folding a $2\frac{1}{2}$ " pleat. Place first foldline $6\frac{1}{2}$ " in from side seam on both Front (1) and Back (2) pattern pieces.









Adjusting Length:

•Add 8½" (or desired amount) to hem length on Front (1) and Back (2) pattern pieces.

Adjusting Pattern Markings for Side Slits:

•Draw two new dots A and B to mark new side seam. Dot A: place along same horizontal line as original dot, out 1 5/8" from side edge. Dot B: place 5 ½" down from Dot A.





Instruction Adjustments:


Back and Shoulder Seams:

Complete instructions as written in Plaza Jacket Guidesheet.

Pressing Hems:

Using the 1 5/8" template, place template on the wrong side, press raw edges of center fronts, side seams, back neckband, and front and back hems up and over bottom edge of template so raw edge is even with top of the template.

Open out pressed hems. Place 1 1/4" template on the fold of previously pressed hem and press raw edge over template making a 1 1/4" finished hem. *Do not topstitch yet*.




Mitering Corners:

Complete instructions as written, mitering six corners on Front and Back.

Side Seams:

Open out pressed hem on sides. With right sides together, using a 1 5/8" seam and hem foldline as a guide, stitch side seam from A to B, backstitching at each dot. Press seam open.



Hems:

Complete **SLIPSTITCH** instructions as shown on back neck facing.

Repress hems at center front, *side seams*, lower front and back. Hand baste in place. **TOPSTITCH**.